



Equipment Manager Release Notes

VERSION 1.3

BOURQUE LOGISTICS

DECEMBER 2025

Confidentiality Notice

This document contains confidential information and trade secrets of Bourque Logistics, Inc. It is intended solely for the use of authorized Bourque licensees. Unauthorized use, distribution, or disclosure is strictly prohibited.



EQUIPMENT MANAGER

RELEASE NOTES

VERSION 1.3

Enhancements

- Reworked dynamic queries for all Equipment grids to be more performant.
- Add, update, delete of a Reporting Category causes this information to be added, updated, or removed from the Available Columns list in Equipment, Equipment Components, and Rail Equipment Current Dates grids.
- Add, update, delete of a Mechanical Field causes this information to be added, updated, or removed from the Available Columns list in Equipment and Equipment Components.
- Add Owner Type to Components, Component Categories, and Equipment Categories. Prevent users from deleting or editing any system generated data.
- Add ability to import additional Lease Rental records on an existing Lease Rider in order to set the Lease Rider Effect Date earlier or Lease Rider Expire Date later.
- Add ability to add a new Lease/Sublease on an existing Asset Assignment through Importer in which the new Lease/Sublease starts on an earlier pre-existing Asset Assignment if allowed.
- Add conditional requirements for Lease/Sublease information on Asset Assignment imports based on information included in the upload.
- Allow multiple Fleet Assignments on the same Equipment through Importer. If the user does not include the Expire Date on these, they will be set automatically based on the data in Importer, as well as existing assignments for that Equipment.
- Allow multiple Asset Assignments without Leases/Subleases on the same Equipment through Importer. If the user does not include the Expire Date on these, they will be set automatically based on the data in Importer, as well as existing assignments for that Equipment.
- Allow multiple Asset Assignments with Leases/Subleases on the same Equipment through Importer if there are no existing assignments. If the user does not include the Expire Date on these, they will be set automatically based on the data in Importer.
- Automatically assign all Equipment that is associated with Rail Transit Mode to the RAIL-ALL Equipment Category and RAIL ALL FITTINGS Component Category. This is assigned both in the application and through Importer.
- Add information about the number of cars or components affected by deleting a Mechanical Field.
- Update User Role Names to be more descriptive.
- Update Mechanical Field names for consistency in FASTRAC Available Columns and in Importer templates.
- Return more user-friendly information when a user attempts a disallowed action.
- Prevent updating Lease Type on a Lease Rider through Importer if there is any Equipment associated with this Lease Rider.
- Prevent updating Data Type or Field Type on an existing Mechanical Field.
- Remove unused fields on Mechanical Field form.
- Ensure that the Fraction Digits does not exceed the Total Digits assigned for a Mechanical Field that is numeric.



EQUIPMENT MANAGER

RELEASE NOTES

VERSION 1.3

- Prevent the Actual Arrival Date for an Asset Assign or Equipment Lease/Sublease from being outside the date range of that assignment.
- Allow deleting a Component Category used by Equipment if there are no Components assigned to that category.
- Prevent changing the Transit Mode on an Equipment Category if it has been assigned to any Equipment.
- Add validation to prevent users from importing a value of 0 for Equipment Compartments.
- Add Lease Party No to Lease Party Name dropdowns on Equipment Lease form.
- Retrieve trip information for Rail Equipment Current Dates grid, even when the trip does not include a commodity.
- Remove defaulted Actual Arrival Date on new Asset Assign or Equipment Lease/Sublease. Include warnings that if not Actual Arrival Date, the Lease History will not be set instead.
- Remove Actual Arrival Date in Asset Assign if adjusting Begin/End Dates causes it to fall outside of the Assignment date range.
- Convert data that is displayed differently in RAILTRAC and in Equipment to have the correct appearance in the applications.
- Set default RAILTRAC units of measure when syncing data to Equipment.
- Run conversions to use default RAILTRAC units of measure if Equipment has used a different unit of measure when syncing from Equipment to RAILTRAC.
- Set default Car Type and No of Compart when syncing data from RAILTRAC to Equipment.
- Set up sync between RAILTRAC and Equipment for Lease data. Set default Currency.
- Use the most recent retired Equipment Lease during sync if there are multiple potential options based on Actual Arrival Date.
- Allow syncing of bulk delete operations on Equipment with RAILTRAC.

Resolutions

- Bug fix – adding an extra RAILTRAC Lease History record when updating a Lease Actual Arrival Date through Importer.
- Bug fix – RAILTRAC Lease History record not removed when deleting an Asset Assignment along with its associated Equipment Lease record in Equipment.
- Bug fix – prevent adding a Lease/Sublease prior to the start of an Asset Assignment that allows this type of Lease/Sublease.
- Bug fix – allow users to enter dates in grids as m/d/yy with no error.
- Bug fix – remove unused dialog appearing when user is editing a Lease Rider Rental.
- Bug fix – allow Car Type to be 1 character.
- Bug fix – expire prior assignment when a more recent Asset Assign or Fleet Assign is added to RAILTRAC.